


EXO Handheld and Sonde Firmware Change Notes



Purpose:

This document contains release notes for the firmware relating to EXO Sondes, Handhelds, and Sensors.

Instrument	Latest Version
EXO Sondes	
EX01, EX02, EX03	1.0.86
EXO Sensors	
pH, ORP, NH ₄ , Cl, NO ₃ , fDOM	3.3.0
Turbidity	3.0.5
C/T, Wiped C/T, ODO, TAL-PC, TAL-PE	3.0.5
Central Wiper	3.0.11
Depth	3.1.3
Rhodamine	3.1.10
NitraLED	1.0.59
EXO Accessories	
EXO Handheld	1.0.72
EXO GO	1.0.21
SOA-DCP	2.0.14
SOA-Modbus	2.0.16

Turbidity Firmware v3.0.5
August 2024

What's New:

Improved Turbidity sensor calibration process..

Change Notes:

- Adjustments made to QC range to improve the accuracy of the Turbidity sensor calibration process

SOA-Modbus Firmware v2.0.16
March 2024

What's New:

Bug fix to improve SOA-Modbus interfacing with Blu-X.

Change Notes:

- Improvements to the SOA-Modbus interface with Blu-X

PREVIOUS UPDATES

EXO Handheld Firmware v1.0.72

February 2023

What's New:

Bug fixes to improve calibration recording.

Change Notes:

- Fixed an issue in calibration record for pH and ISE sensor value (mV) reading
- Fixed minor issue in calibration record where the barometer was listed as an "Unknown" device type. Changed to "Handheld" for consistency with DSS platform

EXO Handheld Firmware v1.0.70

March 2022

What's New:

Bug fixes to improve calibration recording and functionality.

Change Notes:

- Fixed pre-calibration values for Kor calibration record parsing
- Fixed issues with barometer calibration record for Kor calibration record parsing
- Added wiper mode to GLP and Kor calibration record
- "Start Logging Now" changed to start logging immediately even if there is a discrepancy in time between the handheld and sonde

EXO Handheld Firmware v1.0.63

September 2020

What's New:

Additional support for sensors and language options.

Change Notes:

- Added support for NitraLED Sensor and Depth/Temperature Sensor
- Fixed issue with the barometer display for non-GPS units
- Added more language options

EXO Sonde Firmware v1.0.86

July 2020

What's New:

Bug fix for EXO Sonde depth sensor.

Change Notes:

- Fixed issue with updating depth sensor



YSI Incorporated
1725 Brannum Lane
Yellow Springs, OH 45387

Tel +1 937.767.7241
Email info@ysi.com
YSI.com

All information presented herein is believed reliable and in accordance with accepted engineering practices. Xylem makes no warranties as to the completeness of this information. Users are responsible for evaluating individual product suitability for specific applications. Xylem assumes no liability whatsoever for any special, indirect or consequential damages arising from the sale, resale or misuse of its products. Subject to change without notice.

© 2024 Xylem Inc. or its affiliate. All rights reserved. EXO is a trademark of Xylem or one of its subsidiaries.

XA00309-02 1224

xylem
Let's Solve Water